ວິທີລົງ windows 7

ສິ່ງທີຕ້ອງກຽມຄື:

- 1. ຄອມພິວເຕີ ທີ່ຈະລົງ
- 2. Windows 7/8/8.1/10
- 3. ໂປຣແກຮມອັດໄຟລ: Rufus USB-tool, PowerISO7-x64
- 4. ແຜນ DVD ຫຼື USB ກໍໄດ້
- 5. ຕ້ອງໄປດາວໂຫລດ Driver ມາໄວ້ກ່ອນທີ່ຈະລົງ Windows
- I. ເປີດ Rufusອອກມາ

Rufus 2.15.1117	
Device	0 •
NO_LABEL (I:) [32GB]	•]
Partition scheme and target syster	n type
GPT partition scheme for UEFI	•
File system	
NTFS	•]
Cluster size	
4096 bytes (Default)	•
New volume label	
GSP1RMCENXVOL_EN_DVD	
Format Options 💟	
Check device for bad blocks	1 Pass 🔹
Quick format	
Create extended label and ico	in files
READ	οv
About	Start Close
and a state of a strengther with	
: en_windows_/_enterprise_with_	spi_xo4_ava_u #

ll. ຫຼັງຈາກເລືອກ Windows 7 ແລ້ວ ກົດ Start

	130 tingle		3
Create extended label a	nd icon files		
e e	T 1400		
Creating file syst	em: Task 1/12 comp	leted	
Creating file syst	em: Task 1/12 comp	leted	ancel
Creating file syst	em: Task 1/12 comp	leted	ancel

lll. ໄດ້ windows ເຂົ້າໃນ DVD ຫຼື USB ແລ້ວ

Microsoft Store		_ ×
WINDOWS 7 USB/DVD DOWNLOAD TOOL		Online help
Bootable USB device created su	ccessfully	• •••••
© copyright WWW.Windowssiam.com	© Copyright WWW.W	vindowssiam.com
Status: Backup completed.		100%

Date modified
10/1/2017 12:48 PM
10/1/2017 12:48 PM
10/1/2017 12:52 PM
10/1/2017 12:52 PM
10/1/2017 12:52 PM
10/1/2017 12:48 PM

IV. ເອົາແຜນ DVD ຫຼື USB ທີ່ມີ windows ຢູ່ ແລ້ວສຽດເຂົ້າໄປໃນ ຄອມພິວເຕີ ແລ້ວປິດ ກົດຄຳສັ່ງເພື່ອ Boot Bios



ຕິດຕັ້ງ Bios ກົດ Enter ເພື່ອເຂົ້າສູ່ Windows



Language to install : เดือก English

V. Keyboard or input method : ເລືອກ Language US

👋 Install Windows	
VVIndows	
Languag <u>e</u> to install: <mark>English</mark>	
Time and currency format: English (United States)	
Keyboard or input method: US	
Enter your language and other preferences and	I click "Next" to continue.
Copyright © 2009 Microsoft Corporation. All rights reserved.	Next
© Copyright WWW.WindoWssiam.com	@ Copyright WWW.Window siam.cv/n

ກົດ Next

vi. ກົດ Install Now



VII. ກົດໝາຍຕິດໃຊ້ I accept the license terms > ກົດ Next

MICR	DSOFT SOFTWARE LICENSE TERMS
WIND	OWS 7 PROFESSIONAL
These where softwa Printe any or	license terms are an agreement between Microsoft Corporation (or based on you live, one of its affiliates) and you. Please read them. They apply to the are named above, which includes the media on which you received it, if any. d-paper license terms, which may come with the software, may replace or modify n-screen license terms. The terms also apply to any Microsoft
• u	odates,
. sı	ipplements,
• In	ternet-based services, and

viii. ເລືອກ Custom (advance)

j.	Upgrade Upgrade to a newer version of Window The option to upgrade is only availabl running. We recommend backing up	ws and keep your files, settings, and programs. e when an existing version of Windows is your files before you proceed.
	<u>C</u> ustom (advanced) Install a new copy of Windows. This o programs. The option to make change start your computer using the installat before you proceed.	ption does not keep your files, settings, and es to disks and partitions is available when you tion disc. We recommend backing up your files
<u>i</u> elp me d	ecide	

IX. ເລືອກ ຊ່ອງ ທີ່ຕ້ອງການຈະລົງ Windows ໃຊ້ ເພື່ອແບ່ງ Harddisk ເປັນ Partition

020 76650659

Khammunh Thao

	Name	Total Size	Free Space	Туре
3	Disk 0 Unallocated Space	100.0 GB	100.0 GB	

ກົດ New >

10. Size ໃຫ້ແບ່ງ Harddisk Drive C ທີ່ເຮົາຢາກໄດ້ເຊັ່ນ: 100 GB ກໍໃຫ້ເອົາ 1024 ຄູນຈະໄດ້ 102400 MB (ຂໍແນະໃຫ້ Drive C = 100 GB)

020 76650659

Name		Total Size	Free Space	Туре
🚙 Disk 0 Una	llocated Space	100.0 GB	100.0 GB	
ۥ Refresh	Delete	Format	New	

12. ໃຫ້ເລືອກ Drive ທີ່ເຮົາແບ່ງໄວ້ Drive : C ໂດຍການຄລິກ Drive ນັ້ນແລະ ກົດ Next

	Name		Total Size	Free Space	Туре
P	Disk 0 Partiti	on 1: System Reserved	100.0 MB	86.0 MB	System
30	Disk 0 Partiti	on 2	99.9 GB	99.8 GB	Primary

13. ໃຫ້ໄປເລືອກ Drive ທີ່ເປັນ Drive C ແລ້ວກົດ Format ຫຼັງຈາກ Format ແລ້ວ Drive C ຂອງ ເຮົາເປັນ Drive ໃໝ່. (ຂໍ້ຍົກເວັນ:ໃນການຈະລົບ **Partition ຕ້ອງລົບຊ່ອງທີ່ມີ Windows ເທົ່ານັນ.** ຖ້າລົບໄດ້ ຂໍ້ມູນເຮົາຈະເສຍ)

	Name	Total Size	Free Space	Туре
S	Disk 0 Partition 1: System Reserved	100.0 MB	86.0 MB	System
3	Disk 0 Partition 2	99.9 GB	99.9 GB	Primary

14. ຈາກນັ້ນໃຫ້ເລືອກເອົາ Drive C ທີ່ເຮົາ format ໄປ > ກົດ Next

N	ame	Total Size	Free Space	Туре
🧼 Di	sk 0 Partition 1: System Reserved	100.0 MB	86.0 MB	System
🧼 Di	sk () Partition 2	00.0.00	00.9 GR	Driman
		40 6.66	35/0 00	rinidy
€ <u>y</u> <u>R</u> efresh	<u>Noruntion 2</u> <u>D</u> elete	Solution Sector	* N <u>e</u> w	rinidy

15.ຂັ້້ນຕອນນີພງງແຕ່ລໍຖ້າເທົ່ານັ້ນ ໃຫ້ຮອດ 100% ກ່ອນ



16.ໃຫ້ຕັ້ງຊື່ <u>Type a user name :</u> ໃນ <mark>User</mark> ຂອງຄອມພິວເຕີເຮົາ

🌀 ਗ਼ Set Up	Windows
	Mindows [:] 7 Professional
Choose a l	user name for your account and name your computer to distinguish it on the network.
	Type a user name (for example, John):
	admin
	Type a <u>computer name</u> :
	admin-PC
	www.windowssiam.com
•	Copyright © 2009 Microsoft Corporation. All rights reserved.
	Next
	- THERE

17. ໃຫ້ໃຊ້ Password (ແຕ່ຖ້າບໍ່ໃຊ້ກໍໄດ້ ຫຼື ໃຊ້ຕ້ອງໃຫ້ຈື່)

Set a p	assword for your	r account			
Creating unwante	a password is a smart d users. Be sure to ren	security precaution nember your pass	on that helps protect word or keep it in a s	your user account f afe place.	rom
Type a p	assword (recommend	ed):			
		5			
Retype y	our password:				
Type a p	assword hint:				
Choose If you fo	a word or phrase that H rget your password, W	helps you rememł /indows will show	eer your password. you your hint.		

18. ໃສ່ Product Key Windows 7



19. ສໍາລັບໄດ໌ທີ່ເຮົາ Windows 7 ແທ້ໃຫ້ເລືອກ User Recommended Settings ໃນການ Update



20. ຕັ້ງເວລາ Windows

Tim	e zor	ne:										
(UT	C+07	7:00)	Bang	gkok,	Har	noi, Jakart	a			•		
Date	5						Time:					
•		Octo	ber.	2014		•	1	(11) (11) (11)				
Su	Mo	Tu	We	Th	Fr	Sa	1	/	1			
28	29	30	1	2	3	4	1	1	1			
5	6	7	8	9	10	11	1	-				
12	13	14	15	16	17	18	-					
19	20	21	22	23	24	25	1		1.			
20	21	28	29	30	31	1		- die	/			
2	2	4	2	0	1	õ	9	04:21 PM	1			
							9:	04: ZI PN				

21. ເລືອກPublish Network

Select	t your computer's current location
This co setting	mputer is connected to a network. Windows will automatically apply the correct network s based on the network's location.
2	Home network
1	If all the computers on this network are at your home, and you recognize them, this is a trusted home network. Don't choose this for public places such as coffee shops or airports.
F	Work network
	If all the computers on this network are at your workplace, and you recognize them, this is a trusted work network. Don't choose this for public places such as coffee shops or airports.
-	Public network
7	If you don't recognize all the computers on the network (for example, you're in a coffee shop or airport, or you have mobile broadband), this is a public network and is not trusted.
If you a	aren't sure select Public network

22.ສຳເລັດ Windows 7 USB / DVD



ສຳເລັດ Windows 7 USB / DVD